

TRAVERSE Hardware Requirements and Supported Platforms

Revised 08/01/09

(Note: Latest service packs should be loaded for all software products)

Version 10.5x

Hardware:

	Workstation	Dedicated Server
Minimum Required	Processor: 500 Mhz or higher 256 MB RAM	Processor: 1 Ghz or higher 512 MB RAM
Recommended	Processor: 850 Mhz or higher 512 MB RAM	Processor: 1 Ghz or higher 1024 MB RAM – first 5 users 256 MB RAM/additional 10 users

Server Software:

SQL Database Edition	Operating System
2000 Desktop Engine (MSDE 2000) *	Windows Server 2003 (All editions) Windows XP (Professional)
2005 Express * (Included with TRAVERSE)	Windows Server 2008, 2008 R2 (All editions) ^{1 2} Windows Server 2003 (All editions) Windows XP (Professional)
2008 Express *	Windows Vista (Business or Ultimate) Windows 7 (Professional or Ultimate)
2005 Workgroup *	Windows Small Business Server 2003
2000 Standard or Enterprise	Windows Server 2003 (Standard, Enterprise or Datacenter) Windows 2000 (Server, Advanced Server or Datacenter)
2005 Standard or Enterprise (32-bit) 2008 Standard or Enterprise (32-bit)	Windows Server 2008, 2008 R2 (Standard, Enterprise or Datacenter) ^{1 2} Windows Server 2003 (Standard, Enterprise or Datacenter) Windows Vista (Business, Enterprise or Ultimate) Windows 7 (Professional or Ultimate)
2005 Standard or Enterprise (x64) 2008 Standard or Enterprise (x64)	Windows Server 2008, 2008 R2 (Standard, Enterprise or Datacenter) ^{1 2} Windows Server 2003 (x64 Standard, Enterprise or Datacenter)
2000 Developer	Windows Server 2003 (Standard, Enterprise or Datacenter) Windows 2000 (Professional, Server or Advanced Server) Windows XP (Professional)
2005 Developer (32-bit) 2008 Developer (32-bit)	Windows Server 2008, 2008 R2 (Standard, Enterprise or Datacenter) ^{1 2} Windows Server 2003 (Standard, Enterprise or Datacenter) Windows XP (Professional) Windows Vista (Business, Enterprise or Ultimate) Windows 7 (Professional or Ultimate)
2005 Developer (x64) 2008 Developer (x64)	Windows Server 2008, 2008 R2 (Standard, Enterprise or Datacenter) ^{1 2} Windows Server 2003 (x64 Standard, Enterprise or Datacenter)

Workstation Software:

MS Access Version	Operating System
2003 (Version 11) (Full version or run-time) (Run-time included with TRAVERSE)	Windows XP (Professional) Windows Vista (Business or Ultimate) Windows 7 (Professional or Ultimate)

* The TRAVERSE Advanced Information Analyst application is not compatible with the SQL Server 2000 Desktop Engine, the SQL Server 2005/2008 Express Editions or SQL Server 2005 Workgroup Editions.

¹ For SQL Server 2005, you need to be on SQL Server Service Pack 3 to be compatible on Windows 7/WS08 R2

² For SQL Server 2008, you need to be on SQL Server Service Pack 1 to be compatible on Windows 7/WS08 R2

Version 10.2x

Hardware:

	Workstation	Dedicated Server
Required	Processor: 300 Mhz or higher 128 MB RAM	Processor: 500 Mhz or higher 256 MB RAM
Recommended	Processor: 450 Mhz or higher 256 MB RAM	Processor: 1 Ghz or higher 512 MB RAM – first 5 users 128 MB RAM/additional 10 users

Server Software:

TRAVERSE Edition	SQL Database Edition	Operating System
Business	2000 Desktop Engine (MSDE 2000) * (Included with TRAVERSE Business Edition)	Windows Server 2003 (All editions) Windows 2000 (Professional or Server) Windows XP (Professional)
Business	2005 Express *	Windows Server 2003 (All editions) Windows 2000 (Professional or Server) Windows XP (Professional) Windows Vista (Business or Ultimate) Windows 7 (Professional or Ultimate)
Enterprise	2005 Workgroup *	Windows Small Business Server 2003
Enterprise	2000 Standard or Enterprise	Windows Server 2003 (Standard, Enterprise, Datacenter) Windows 2000 (Server, Advanced Server, Datacenter)
Enterprise	2005 Standard or Enterprise	Windows Server 2003 (Standard, Enterprise, Datacenter) Windows 2000 (Server, Advanced Server, Datacenter) Windows Vista (Business, Enterprise or Ultimate) Windows 7 (Professional or Ultimate)
Enterprise	2000 Developer	Windows Server 2003 (Standard, Enterprise, Datacenter) Windows 2000 (Professional, Server or Advanced Server) Windows XP (Professional)
Enterprise	2005 Developer	Windows Server 2003 (Standard, Enterprise, Datacenter) Windows 2000 (Professional, Server or Advanced Server) Windows XP (Professional) Windows Vista (Business, Enterprise or Ultimate) Windows 7 (Professional or Ultimate)

Workstation Software:

TRAVERSE Edition	MS Access Version	Operating System
Business or Enterprise	2003 (Version 11) (Full version or run-time) (Run-time included with TRAVERSE)	Windows 2000 (Professional, Server or Advanced Server) Windows XP (Professional) Windows Vista (Business, Ultimate) Windows 7 (Professional or Ultimate)

*** The TRAVERSE Advanced Information Analyst application is not compatible with the SQL Server 2000 Desktop Engine or the SQL Server 2005 Express or Workgroup Editions.**

Version 10.0x, 10.1x

Hardware:

	Workstation	Dedicated Server
Required	Processor: 300 Mhz or higher 128 MB RAM	Processor: 500 Mhz or higher 256 MB RAM
Recommended	Processor: 450 Mhz or higher 256 MB RAM	Processor: 1 Ghz or higher 512 MB RAM – first 5 users 128 MB RAM/additional 10 users

Server Software:

TRAVERSE Edition	SQL Database Edition	Operating System
Business	2000 Desktop Engine (MSDE 2000) (Included with TRAVERSE Business Edition)	Windows 98 SE Windows NT 4.0 (Workstation or Server) Windows 2000 (Professional or Server) Windows XP (Professional) Windows Server 2003 (All editions)
Enterprise	2000 Standard or 2000 Enterprise	Windows NT 4.0 (Server or Enterprise) Windows 2000 (Server or Advanced Server) Windows XP (Professional) Windows Server 2003 (Standard, Enterprise, Datacenter)
Enterprise	2000 Developer	Windows NT 4.0 (Workstation, Server or Enterprise) Windows 2000 (Professional, Server or Advanced Server) Windows XP (Professional) Windows Server 2003 (Standard, Enterprise, Datacenter)

Workstation Software:

TRAVERSE Edition	MS Access Version	Operating System
Business or Enterprise	2000 (Office 2000) (Full version or run-time)	Windows 98 SE Windows NT 4.0 (Workstation or Server) Windows 2000 (Professional or Server) Windows XP (Professional)
Business or Enterprise	2002 (Office XP) (Full version or run-time) (Run-time included with TRAVERSE)	Windows 98 SE Windows NT 4.0 (Server or Enterprise) Windows 2000 (Professional, Server or Advanced Server) Windows XP (Professional)